



EXPLANATION

NON-FEDERAL COAL LAND - Land for which the Federal Government does not own the coal rights.

PRLA U6733
PREFERENCE RIGHT LEASE APPLICATION (PRLA) - Showing PRLA number.

ISOPACH - Showing thickness of coal, in feet. Arrow points toward area where coal bed is 5 feet or more thick.

Em - Emery coal zone

COAL BED SYMBOLS AND NAMES - Coal beds identified by bracketed numbers are not formally named, but are numbered for identification purposes in this quadrangle only.

TRACE OF COAL ZONE OUTCROP - Showing symbol of name of coal zone as listed above. Arrow points toward coal-bearing area. Dashed where inferred.

SL - STRIPPING-LIMIT LINE - Boundary for surface mining (in this quadrangle, the 100-foot-overburden isopach). Arrow points toward the area suitable for surface mining where the recovery factor is 85 percent, and away from the area suitable for subsurface mining where the recovery factor is 50 percent.

C - INFERRED LIMIT OF BURNED AND CLINKERED COAL - Arrow points toward area of baked and fused rock.

RB	R(85%)	RB	R(50%)	
0.58	0.49	0.04	0.02	(Measured)
0.56	0.48	0.04	0.02	(Indicated)
				(Inferred)

IDENTIFIED COAL RESOURCES - Showing totals for Reserve Base (RB) and Reserves (R), in millions of short tons, for each section or part of section of non-leased Federal coal land, both within and beyond the stripping-limit line. Reserve (R) tonnage is calculated by multiplying the Reserve Base (RB) tonnage by the appropriate recovery factor. Dash indicates no resource in that category. Reserves have been calculated for a constant thickness of 12 feet for areas where the coal beds are more than 12 feet thick. Therefore, in some instances, underground Reserves may be less than 50 percent of the Reserve Base.

Measured resources (M)
Point of measurement
Indicated resources (I)
Inferred resources (Int)

BOUNDARY LINES - Enclosing areas of measured (M), indicated (I), and inferred (Int) coal resources. Dashed where projected from adjacent quadrangles.

To convert short tons to metric tons, multiply short tons by 0.9072.

To convert feet to meters, multiply feet by 0.3048.

To convert miles to kilometers, multiply miles by 1.6093.

This report has not been edited for conformity with U.S. Geological Survey editorial standards or stratigraphic nomenclature.

COAL RESOURCE OCCURRENCE MAP OF THE SOUTHEAST QUARTER OF THE NOTOM 15-MINUTE QUADRANGLE, GARFIELD COUNTY, UTAH
BY
DAMES AND MOORE
1979